

Custom Setting -> "CC_config"

Custom Setting CC_config

If the custom setting is a list, click **New** to add a new set of data. For example, if your application had a setting for country codes, each set might include the country code.

If the custom setting is a hierarchy, you can add data for the user, profile, or organization level. For example, you may want different values to display depending on the user.

Edit

Delete

▼ Default Organization Level Value

Location	Samurai System	defaultAreaFilter	☐
defaultLat	0.00000000	defaultLon	0.00000000
defaultZoom	15	map_NameFilterForReport	☒
map_NameFilterForView	☒	maxResults	20,000
CCTargetSObjects	lead,account,contact,opportunities	defaultTaskTitle	MyTask
defaultEventTitle	MyEventORG(no info)	CCGeocodingLicenseKey	Z3Un17xaQ6Xv5psjqBslhFQxuARacTEXTMslUQcb/SQl8a1SCTGkD0/n
GoogleMapsClientid		CCMapTitle	CCマップ
cachePage	☐	BatchGeocodingTargetSObjects	lead,account
GeocodingEmailNotification	☒	BatchGeocodingValidUTCTime	11,13,15,17,19,21,23

"Batch Geocoding" functionality is now available.

in CustomSetting -> cc_config -> CCGeocodingLicenseKey, set license key string provided by Samurai System.

Once valid key is set, batch geocoding buttons will be shown on Geocoding Screen.

in CustomSetting -> cc_config -> BatchGeocodingTargetSObjects

Example: if you set "account, lead, contact" in this setting, and push start button on 16:30,

17:00 run Geocoding on "account"

18:00 run Geocoding on "lead"

19:00 run Geocoding on "contact"

20:00 run on "account" again

:

:

New

GeocodingEmailNotification

You can disable email notification when geocoding is completed.

CCGeocodingLicenseKey

To enable batch geocoding functionality, please set license key issued by Samurai System.

BatchGeocodingTargetSObjects

To enable batch geocoding functionality, enter sObject name to run geocoding.

For example, if you need to run batch geocoding on Account and MyObject_c, you may set this as "account,myobject_c".

Batch Geocoding should run at 0 minutes in every hour.

New field "BatchGeocodingValidUTCTime" in CC_config (custom settings)

(Note: Only organization setting is applied.)

Usually, Batch geocoding will be run on every hour 00 minutes.

Now, if you set a list of 'hour', batch geocoding only run at a time in list.

For example,

"BatchGeocodingValidUTCTime" is set as

"11,13,15,17,19,21,23"

that means that Batch Geocoding is run at 11:00, 13:00, 15:00, 17:00, 19:00, 21:00, and 23:00.

Time is UTC(GMT) time, and not local time.

[Search](#)

Developing **CustomerCompass**, latest version

[カスタマー コンパス](#) [Setup](#) [Help & Training](#) [CustomerCompass](#)

[Home](#) [CustomerCompass](#) [CCGeocoding](#) [CCDocumentation](#) [+](#)

[Create New...](#)

[Recent Items](#)

 カスタマー コンパス

Geocoding

Convert from Address to Latitude/Longitude coordinates

Please run for each SObject

和暦アポイント

和暦表示

Recycle Bin

Note: Maximum 50,000 records per 24 hours, per organization

Lead ▼

Start Geocoding

RESET Geocode-failed records (to run again)

Activate Daily Geocoding

Stop Daily Geocoding